



UNIVERSITY OF
BIRMINGHAM



AQUA-FAANG - Standard Operating Protocol - Dechoriation of carp embryos, embryo collection and preparation for ChIP-seq

Overview

This protocol describes a method to remove chorions from carp embryos and to prepare (Cross-link) and preserve embryos at the desired stages.

1. Embryo dechoriation

Materials

- Petri dishes (agarose-coated)
- 500 ml Beakers
- 3ml Paster pipettes

Reagents and solutions:

- 100X E3 medium stock solution: 28,667g NaCl, 1,267g KCl, 4,833g CaCl₂ 2H₂O, 8,167g MgSO₄ 7H₂O in 1l of H₂O. Dilute to 1X for working solution and add 0.00001% of methylene blue
- Pronase: 10 mg/ml pronase solution
- Agarose

Preparation of agarose coated petri dishes

1. Prepare and dissolve 1% agarose solution in 1X E3 with 0.00001% methylene blue.
2. Aliquot the agarose solution into petri dishes adding enough volume to cover one-third of the height of the petri dishes.
3. Allow the agarose to polymerize. Store agarose-coated plates at 4 degrees and return to room temperature before using them with embryos.

Dechoriation procedure

1. After fertilization, wait some minutes for chorions to swell up. Carp embryos are sticky so they need to be scraped out of the surface where they are deposited and collected in a petri dish. Alternatively, perform *in-vitro* fertilization directly on a petri dish and wait for the chorions to swell up.
2. Remove the embryo water and replace it entirely with a 10mg/ml pronase solution.
3. Incubate the embryos at room temperature.
4. **KEY STEP:** During pronase incubation check the embryos under the microscope to observe chorion softening. When some chorions have started to break, the pronase will be ready to be washed.

5. Fill the beakers with E3 medium and immerse the embryos very gently in it without letting the embryos touch the air.
6. Wait for the embryos to fall into the bottom and remove as much medium as possible and repeat the wash in step 5 by gently pouring the liquid through the walls of the beaker.
7. Repeat washing steps (5 and 6) 5 times until the pronase has been completely washed out.
8. Cut the tip of a pasteur pipette until the diameter is big enough to pass one embryo easily.
9. Fill the room-temperature agarose-coated petri dishes with E3 medium
10. Using the pasteur pipetter prepared in step 8, transfer the embryos to the agarose coated petri dishes making sure that just the intact embryos are selected.
11. Wait 10 minutes for the embryos to sit on the plate and remove any possible debris or spoilt embryo.
12. Take the dish to an incubator.

Notes:

- The general advice is not to wait until many chorions show cracks or softening as this will lead to overdigestion and embryo death.
- If some chorions remain after this procedure, it is now easy to remove them by gently pulling them apart with dechoriation tweezers. These chorions have to be cleaned out of the fish medium as they contain pronase which will affect the embryo development.
- Embryos dechorionated at the 1-cell stage should be re-checked after 5-7 hours when any dead embryos have to be removed to improve the survival of the batch.
- E3 medium has to be changed on a daily basis.

Recommended embryo number per replicate and downstream application

	Late blastula	Gastrula	Early somitogenesis	Mid somitogenesis	Late somitogenesis	Pharyngula
RNA-seq	20	20	10	10	5	5
ATAC-seq	20	10	10	10	5	5
ChIP-seq	40	40	20	20	15	10

2. Embryo preparation and preservation for ChIP-seq

1. Collect embryos in 1.5 ml tubes and prepare for crosslinking, remove all supernatant.
2. Proceed to Crosslinking using 875 µL of 1% formaldehyde.
3. Stop crosslinking 125 µL of 1M Glycine, followed by resuspension in 1 mL of PBS
4. Store at -80°C.